

## Detroit Diesel Diagnostic Link(r) 6.46 Readme

### CONTENTS

- Features / Revisions
- System Requirements
- Installing Detroit Diesel Diagnostic Link
- Un-Installing Detroit Diesel Diagnostic Link
- Notes on clearing trip data with DDDL
- How to extract trip data from a vehicle and create reports
- Known outstanding issues

### DDDL 6.46 Enhancements:

- This is a stand-alone version of DDDL. DDEC Reports 7.01 will be provided separately.
- DEF (Diesel Exhaust Fluid) fields added
- Trip Activity Report expanded to two pages to accommodate the new fields

### DDDL MINIMUM SYSTEM REQUIREMENTS

**IMPORTANT NOTE:** As the diagnostic and reprogramming software applications have evolved, the requirements for additional computer storage capacity and memory has increased. Please review these computer specifications carefully and take any necessary steps to update your hardware as needed.

#### Component Minimum

- Windows XP, Windows Vista or Windows7 (32 & 64 bit)
- 1.8 Ghz processor
- 1.0 GB RAM
- 40 Gigabyte Hard drive with 20 Gigabyte free
- 32x CD ROM Drive
- Monitor and graphics card supporting 1024 x 768 resolution and 16-bit color
- 1 free USB port
- Internet or Mainframe Connection to DDC Server (for updates)

#### Hardware Adapter Device (One of the following)

› Nexiq USB-Link with USB cable (Required for Cascadia diagnostics)

\* Laptops purchased from Detroit Diesel beginning in August 2006 meet the minimum specifications. Any purchase prior to this time may need to be upgraded.

#### Component Recommended

- Windows XP, Windows Vista or Windows7 (32 & 64 bit)
- 2.0+ GHz Dual-Core processor
- 2 GB RAM or more
- 100 GB hard drive with 20 GB free space
- DVD ROM drive
- Monitor and graphics card supporting 1280 x 1024 resolution and 32-bit color
- Parallel port, three free USB ports
- High Speed Internet – Broadband Internet

#### Hardware

Adapter device (One of the following)

- › Nexiq MagiKey device with parallel cable
- › Nexiq USB-Link with USB cable (Required for Cascadia diagnostics)

Note: Bluetooth functionality NOT approved at this time  
Operating System Windows XP, or Windows Vista Business, Ultimate, or Enterprise

DDDL 6.46 is installed with DDDL or DDRS 7.X

#### UN-INSTALLING Detroit Diesel Diagnostic Link

- 1) Select "Settings | Control Panel" from the "Start" menu.
- 2) Select the "Add/Remove Programs" icon.
- 3) Select "Detroit Diesel Diagnostic Link" from the list.
- 4) Click the "Add/Remove..." button.
- 5) Click the "Next" button in the dialog that appears to choose "Automatic Uninstall".
- 6) Click the "Finish" button to perform the Uninstall.